Scanguns Configuration 3.1.4 Locking Down Logon Pad Configuring SAP Logon Pad Lockdown

There may be times when it is necessary to lock down the SAPLOGONPAD and restrict users' ability to create, edit or select connections. To lock down the logon pad, first ensure that a default connection is set and that the LiquidUI-Mobile.sy3 file attribute is set to 'read-only. Once these two actions are complete, please do the following:

- 1. **Copy** the existing LiquidUI-Mobile.sy3 file from the device to the desktop. **Note**: You can use ActiveSync to access the sy3 file on the device.
- 2. Right-click on the sy3 file on your desktop and choose Properties.
- 3. Uncheck the 'Read-only' option if it is checked. **Note**: You must uncheck this option in order to edit the sy3 file.
- 4. **Copy** the sy3 file back to the device.
- 5. **Launch** Liquid UI for Handheld Scanguns on your device and select a system.
- 6. In the Logon Pad, select the default connection.
- 7. In the default connection, click Properties > Profile Management.
- 8. **Select** the profile you wish to modify and click Edit Profile... as shown below.

🏄 GuiXT Mobile Log: 💡 🗱 🎢 📢 ok			
General			
Description Test			
Application Server testSAP			
SAProuter String			
System Number 0			
Profile			
No profile selected 👻 Edit Profile			
Profile Management			
OK Cancel			

9. **Check** the Super Limited checkbox as shown below.

Page 1 / 3 (c) 2024 Liquid UI | Synactive | GuiXT <dev@guixt.com> | 2024-07-31 19:00 URL: https://www.guixt.com/knowledge_base/content/45/473/en/314-locking-down-logon-pad.html

Scanguns Configuration

👭 GuiXT M	obile Logon 🛛 井	Yıl € ok	
User Restrictions Super Limited Reconnect after logout Disable Command Entry Box			
Server Response Timeout (sec) 144 Suppress Table Control Suppress Waiting Response Window V 'X' Behaves Like Windows			
Profile Setting	Advanced Setting	Misc. User	

- 10. Click OK to save your settings and exit the profile manager.
- 11. **Copy** the sy3 file from your device to your target system.
- 12. **Open** the file properties and set the sy3 file to 'Read-only' and then copy it back to the device.

Note: You must set the sy3 file to be read-only in order to lock down the logon pad.

13. **Start** the Liquid UI Handheld Scanguns application on your device. The Logon button should appear grayed out as in the example below.

Scanguns Configuration



Note: If the logged-on session is still available, you can click the Show Session button to view the current SAP session. Click Exit to quit the logon pad.

Unique solution ID: #1473 Author: Shilpa Sahu Last update: 2019-07-02 12:50